

Function MM - Message Maintenance (Administrator)

This function allows modification of Complete messages definitions.

If you select the MM option from the UUTIL menu, the Message Maintenance menu is displayed:

```

15:14:40          TID      9          TEST-611          User COK          20.02.02
                  --- Message Maintenance ---          UTM7

Fc Function.....: Fc Function.....:
--- -----
DI Display message LS List messages
ED Edit (Update) message TR Translate to another language
--- -----
```

Function:

Group:

Msg number ...: 0 to: 9999
Language: 1 to: 1

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
End

Meaning of the input fields:

Field	Meaning
Function	<p>Available functions are:</p> <ul style="list-style-type: none"> DI Display messages ED Edit (update) message LS List messages TR Translate to another language
Group	Group to which the message belongs. This is usually the utility name or a code for internal Complete functions (for example, UPF, ZSR, ULG, ABS, ...).
Msg Number	Message number to be displayed (single message), or a range to restrict the message display. Valid range is 0 to 9999.

```
16:20:00      Tid    12      TEST-611      User MBE      13.11.00
System:          --- Message Maintenance ---      UTM8

MsgId.: ULG0001      Language:   1

.....*....1....*....2....*....3....*....4....*....5....*....6....*....7.
Logon failed for TID $1 (LU=$2): Terminal I/O error in U2QUERY

MVS WTO Routing codes: 1234567890123456      Descriptor codes: 1234567890123456
.....*....1....*....2....*....3....*....4....*....5....*....6....*....7.

Send to terminal in conversation.: .      Abend the program .....: .
Retain in the message logfile....: X      Snap (take a dump) and continue...: .
Send to the system console .....: X      Do not take a dump .....: .
CAPTURE the message .....: .

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
End      Updat      Prev      Next      Purge      Quit
```

Update Message

To update a message, enter appropriate parameters in the input fields and press ENTER. If you are updating an existing message, the message definition is displayed.

You can modify various options concerning each message. The available options in the display speak for themselves. On the left, specify the message destination. On the right, specify system behavior with the message. An option is selected by marking it with an "X" and pressing PF5.

Below is an example of an existing message:

```

16:20:00      Tid   12      Com-plete      User MBE      13.11.00
System:          --- Message Maintenance ---      UTM8

MsgId.: ULG0001      Language:   1

.....*.....1.....*.....2.....*.....3.....*.....4.....*.....5.....*.....6.....*.....7.
Logon failed for TID $1 (LU=$2): Terminal I/O error in U2QUERY

MVS WTO Routing codes: 1234567890123456      Descriptor codes: 1234567890123456
.....*.....1.....*.....2.....*.....3.....*.....4.....*.....5.....*.....6.....*.....7.

Send to terminal in conversation.: .      Abend the program .....: .
Retain in the message logfile....: X      Snap (take a dump) and continue...: .
Send to the system console .....: X      Do not take a dump .....: .
CAPTURE the message .....: .

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
End      Updat      Prev      Next      Purge      Quit

```

You can perform functions on messages by pressing one of the following PF keys:

PF Key	Function
PF3	Back to the previous screen. This can be the main menu (if you have selected function ED) or the selection list (if you have selected function SL). Any modifications not confirmed with PF5 are lost.
PF4	Modify additional data available for this message (for example, explanation, system action). See the section Additional Text Data below.
PF5	Saves modifications made to a message to disk.
PF7	Displays the message with the next lower number in the current group.
PF8	Displays the message with the next higher number in the current group.
PF10	Purges (deletes) any existing updates.
PF12	Leaves the MT subfunction.

Select Messages from a List

If you select function code LS from the message menu, a list of messages is displayed.

17:14:39 TID 15 COM-5.1. User MBE 18.04.97
System: Global --- Message Maintenance --- UTM5

S Grp/Msg Text

OPC0000 &CMON IS INITIALISED.
OPC0001 \$1 \$2 COMPLETED.
OPC0002 \$1: \$2 IS NOT LOGGED ON.
OPC0003 UNRECOGNIZED COMMAND: \$1.
OPC0004 \$1 \$2 \$3ID=\$4 - DEVICE NOT SUPPORTED.
OPC0005 INVALID EOJ COMMAND FORMAT.
OPC0006 \$1 \$2 - TID, LID, OR GROUP INVALID OR NOT DEFINED.
OPC0007 \$1 \$2 - ALREADY ACTIVE.
OPC0008 \$1 \$2 COMMAND INVALID FOR REMOTE TID.
OPC0009 \$1 \$2 ALREADY ALLOCATED TO Com-plete.
OPC0010 \$1 \$2 MULTIPLE TERMINAL CANCEL NOT ALLOWED.
OPC0011 \$1 \$2 COMMAND INVALID FOR LID.
OPC0012 \$1 \$2 - CANCEL DELAYED; IN Com-plete OR PV PROGRAM.
OPC0013 \$1 \$2 TID/LID MUST BE IGNORED PRIOR TO DELETING.
OPC0014 \$1 \$2 NOT ALLOCATED TO Com-plete.

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
End Next Quit

You can enter any character in the S column preceding the desired message to display the message.